## How to save Point Cloud Data from camera

- 0. OS == Ubuntu18.04
- 1. Environment Setting
  - pip3 install OpenCV-Python==4.1.0.25
  - pip install pyyaml==6.0
  - pip install pyrealsense2
  - pip3 install open3d
  - pip install opency-contrib-python==4.1.0.25
- 2. Aruco Marker
  - Print out the attached marker file(3 markers.)
  - Marker 101 should be placed in the corner of the rest of the markers
- 3. Bin setting
  - bin.yml have information of size of bin.
- 4. Run store\_workspace\_info.py to make ROI.
- 5. Run save\_pcd.py to save pcd data.
- 6. Pcd data will be saved in pcd\_data folder.